

Reminder concerning System Manager (MS-DOS) configurations 5620 - 5623

Resellers are reminded that before installing System Manager (MS-DOS) configurations 5620, 5621, 5622 and 5623 it is necessary to perform the following steps (in addition to running ALLOCATE.EXE) after copying the contents of the BACNAT diskette to the MS-DOS hard disk:

1. Rename SSD.INI to GSM.INI
2. Rename SSDBOOT.BAT to GSMBOOT.BAT
3. If System Manager is installed on Windows then it is also necessary to modify the GSMBOOT.PIF file.
Run the PIF editor (usually found in the Main Window) and open the GSMBOOT.PIF file. Change the optional parameter from "GSM200.VOL W" to "GSM200 W". Exit the PIF editor, saving the changes.

The next release of the System Manager (MS-DOS) BACNAT software will include SSD.INI, SSDBOOT.BAT and the modified PIF file as standard components.